


ANGLE & INTENSITY VS. PHASE & AMPLITUDE: a cross-reference

angle description

inclined plane wave:

$$\theta(x,y) = \theta_0$$


wavefront snapshot



phase description

$$\phi(x,y) = \frac{2\pi}{\lambda} \cdot \sin \theta_0 \cdot x$$



“phase footprint”
contours of equal phase
(0° or $n \cdot 360^\circ$)



on-axis spherical wave:

We must restrict our attention to the x - z plane because, for non-zero values of y , the normal to the wavefront tilts out of the plane, and the angle cannot be so simply described.



$$\theta(x,0) = \frac{1}{R_0} x$$



$$\phi(x,y) = \frac{2\pi}{\lambda} R_0 + \frac{\pi}{\lambda R_0} (x^2 + y^2)$$

off-axis spherical wave:

$$\theta(x,0) = \theta_0 + \frac{\cos \theta_0}{R_0} x$$



$$\phi(x,y) = \frac{2\pi}{\lambda} R_0 + \frac{2\pi}{\lambda} \sin \theta_0 \cdot x + \frac{\pi}{\lambda R_0} (\cos^2 \theta_0 \cdot x^2 + y^2)$$

$$\begin{aligned} \text{in general: } \sin \theta(x,0) &= \frac{\lambda}{2\pi} \frac{d\phi(x,y)}{dx} \bigg|_{x,0} \\ &= \cos \theta_x, \text{ or } \ell \text{ in disguise} \end{aligned}$$